



MAXWELL RENDER

Maxwell Render 2.5.1 for Bonzai3d 2.5

Plugin Manual

Plugin version 2.5.2



Compatibility and Versioning	3
Installation	3
Windows or Macintosh	3
Maxwell Key Shortcuts	3
Getting Started	4
Bonzai3d / Maxwell Render Integration	4
The First Step: Making a Rendering	5
Next Step: A Typical Real-World Workflow	6
Render Options	7
Scene	8
Image	11
Camera	12
Simulens	15
File	17
Prefs	20
Lighting	21
Emitter Light Types	22
Point and Cone Lights	23
Softbox	23
IES	24
Environment Light Types	25
Physical Sky	26
Sky Dome	27
IBL (Image Based Lighting)	28
Relative Efficiency of Light Types	29
Lighting with Emitter-Mapped Objects	29
Materials	30
Using 'Translate Shaded'	31
Using 'Referenced MXM'	36
The Online MXM Gallery	37
Tips for Materials and Texturing	38
Organizing Dependency Filepaths	39
Maintaining Dependency Filepaths	39
Maxwell Object Attributes	40
Editing an Object's Maxwell Attributes	40
Importing Projects From FormZ 6	42
Resources and Assistance	43
Troubleshooting	44

Compatibility and Versioning

MaxwellZ plugin version:

- 2.5.2.x

Bonzai versions supported by this plugin:

- Bonzai 2.5 or higher on Windows or OSX.

Maxwell Render versions supported by this plugin:


- Maxwell Render 2.5.1+

Documentation:

- June 2011

Installation

The installation of the Bonzai plugin is an easy and straightforward process.



Pylon Technical (for the artist Jeffrey Neale)
www.pylontechnical.com

Windows or Macintosh

- 1) Install Maxwell Render 2.5.2 or greater.
- 2) Quit Bonzai.
- 3) Delete any previous versions of the Maxwell plugin from the Bonzai3d plugins folder.
- 4) Unzip the MaxwellZ plugin package on your desktop.
- 5) Locate the version of the plugin appropriate for your platform (Windows or OSX), and copy the *Maxwell* directory within to the *Plugins* directory in your Bonzai3d application directory.
- 6) Copy *checker.tif* from the plugin package to the *Support* directory within your Bonzai 3d application directory. This file replaces the checkerboard file used by Bonzai for the Material preview scene, and will provide Maxwell material previews which render faster, exhibit less noise, and describe the material more faithfully. This step is optional but highly recommended.
- 7) Restart Bonzai.

Maxwell Key Shortcuts

- ✓ To get the most out of Maxwell, assign custom key shortcuts to Maxwell Render and Maxwell Render Options. To do so, select *Edit > Key Shortcuts...* from the Bonzai menubar. In the resulting key shortcut dialog, Maxwell may be found by navigating to *Project > Modeling > Display > Static Renderers*. CMD-M (Mac)/ CTRL-M (Windows) works nicely for activating Maxwell. Option-M (Mac)/ ALT-M (Windows) is a good combination for accessing the render options.



"Residence Great Room," Gary Helfand

Getting Started

Bonzai3d / Maxwell Render Integration

This Maxwell Render plugin has been created with the intention of providing an optimum integration of Maxwell Render with Bonzai .

Maxwell Render is integrated in Bonzai by means of two plugins. The principal plugin, *MaxwellZ.fzp*, controls Maxwell Render options and handles the integration of Maxwell materials inside the Bonzai materials palette.

A second plugin, *MaxwellAttributes.fzp*, manages several additional Maxwell-specific attributes which may be added to each Bonzai object.

If you can see "Maxwell Render" as an option in the Bonzai *Display* menu, the plugins are properly installed and enabled.



"Red," Craig Williams, Becker Morgan Group, Inc.

The First Step: Making a Rendering

At it's most basic, rendering a Maxwell image in Bonzai is now a 'one button' process!

1. Open Bonzai and create a new project. The plugin will ask if you want to create a default Physical Sky light. Click 'OK.'
2. Create a few simple objects with different materials on a ground plane.
3. Select Display > Maxwell Render. Maxwell will launch as a separate process and render the current Bonzai view.

If you receive a filepath error, check to see that Automatic filepaths are selected in the *Maxwell Render Options: File* tab.

What Happened

When you selected Maxwell Render, the Maxwell plugin produced a Maxwell Scene File (MXS) based on your Bonzai project, and saved it in the location you specified.

- All visible geometry was translated into Maxwell's internal format.
- All your Bonzai views were included in the MXS file, but the the one that will be rendered is the current view. (The other views can be accessed if you open the scene in *Studio*, Maxwell's standalone scene editor.)
- The scene was set up to be illuminated by the Physical Sky that you created.
- All your active materials were automatically translated into Maxwell Materials and embedded in the MXS file. If your project used RenderZone procedural textures, they were rasterized (converted to bitmap images) and saved in the same folder as the MXS file.
- Finally, the plugin launched Maxwell Render, and instructed it to open the MXS file, to begin rendering, and to save the rendered image at regular intervals.

Next Step: A Typical Real-World Workflow

In practice, you will probably want to adjust the lighting, materials, and render options to achieve a more specific look than provided the defaults. A typical Bonzai/Maxwell workflow follows:

1. Create your geometry in Bonzai.
2. Assign basic Bonzai materials, which will be automatically translated into Maxwell materials. (See *Materials: Using Bonzai Material Automatic Translation.*)
3. Set up basic lighting. The plugin will translate native point and cone lights into the Maxwell scene accurately. There are also many other powerful custom light types that the plugin provides, including *Softbox* (parametric emitter plane), *IES* (measured illumination data from commercial lighting products), *Sky Dome* (fast global illumination environment), *Physical Sky* (sophisticated atmospheric illumination model), and *IBL* (high dynamic range Image-Based Lighting). (See *Lighting.*)
4. Set up views in Bonzai and render. (See *Render Options: Camera.*)
5. Adjust the lights and/or camera exposure and re-render until correct.

that you can interactively adjust the Shutter Speed in Maxwell; when you find a satisfactory value, enter it into the Shutter Speed parameter in Bonzai so that subsequent renderings will be correctly exposed. (See *Render Options: Camera.*)



For test renders, use the 'Render Area Rectangle' to render a smaller section of the image, or set the *Scale* parameter in *Render Options > Image* to a value less than 100%. Note that these two options may be combined.

6. Decide which materials are critical and require the sophistication of Maxwell-defined materials. For these, download free materials from <http://resources.maxwellrender.com/> or create them from scratch using the Maxwell Material Editor. Upon export, the data for each MXMs are embedded in the MXS file. That is, the MXS file does not reference the MXMs, but contains them. (See *Materials: Using Referenced Maxwell Materials.*)
7. When needed, enable advanced effects such as bokeh and rendering channels (*Render Options: Camera*) or Multilight (*Render Options: Scene*).
8. After perfecting the lighting, materials, and composition, generate high resolution finish renderings.



Illustration: Peder Lindbom / AIX architects AB, Client: Setra Group

Render Options

To invoke the Maxwell Render Options dialog/palette, use one of the three methods below:

- Make a custom key shortcut for 'Maxwell Render Options.' This is the preferred method. See the section *Maxwell Key Shortcuts* at the beginning of this user manual.
- Hover over the Maxwell Render Icon in the 'Display Tools' palette. The Render Options palette will appear after about two seconds.
- Select Display > Maxwell Render with the Option / Alt key depressed. Note that after invoking Render Options in this way, Maxwell will begin rendering immediately after dismissing the Render Options dialog.

Each tab in Render Options is dedicated to controlling a different aspect of the rendering process.

Maxwell Render options are stored on both a per-window and a per-scene basis. If you need a more than one set of Maxwell render options in your project, create a window, or alternately, create new Bonzai Scene in the *Scenes* palette for an existing window.

Scene

Maxwell Action

[Maxwell, Studio, None, Network Render, Pack-and-Go Project, Pack-and-Go Scene]
When the user invokes *Maxwell Render* from the display menu, the plugin performs the action specified in this pulldown menu.

Maxwell Action: [Maxwell]

The plugin translates the Bonzai project into an MXS file (Maxwell Scene format), then launches the Maxwell application, which immediately renders the scene described in the MXS file. MXS files contain all scene information, including geometry, cameras, render settings, and materials, with the exception of referenced bitmap images. MXS files are multi-platform, and can be used on Windows, Mac OSX, and Linux alike.

Maxwell Action: [Studio]

The plugin creates the MXS file, then opens the scene in the Studio application. Studio is generally used only in cases where a needed feature is not yet supported by the MaxwellZ plugin. (As of this writing, almost all features are supported.)

Maxwell Action: [None]

The plugin creates and saves the MXS file, but no application is launched. This option is sometimes used in preparation for sending the scene to the Maxwell network renderer.

Maxwell Action: [Network Render]

The plugin creates the MXS file, then launches the Maxwell Network Manager and loads it into the *Add Job Wizard*. See the section titled *The Network System* in the Maxwell user manual for more details.




The use of *Automatic* filename with the *Timestamp* option enabled is recommended when doing network renderings; enabling this will avoid a situation where mxs files might otherwise be overwritten.

Maxwell Action: [Pack-and-Go Project]

This feature packages all pertinent Maxwell-related files (MXM, bitmap textures, and HDRI maps) in preparation for moving your Bonzai project to another workstation. See the manual section titled *Transferring Projects Between Workstations* for more details. Note that MXS scenes and rendered procedural textures are not saved with Pack-and-Go Project, because these are not relevant when transferring a project to another workstation. For convenience, after the Pack-and-Go is exported, the *Maxwell Action* menu will revert to its previous setting. Note: Textures in external MXMs must be referenced correctly in the MXM or they will not be copied. (See the *Troubleshooting* section in this manual.)

Maxwell Action: [Pack-and-Go Scene]



This feature packages all pertinent Maxwell-related files in preparation for rendering a Maxwell scene on another workstation or submitting it to a renderfarm. The plugin creates and saves the MXS file, then copies all rendered procedural textures, bitmap textures, and environment (HDRI) maps into the same folder with the MXS. The resulting MXS folder is completely portable and ready to render anywhere. Note that the 'Create Dependencies Subfolder' (see below) is intentionally not observed with *Pack-and-Go Scene*, for maximum robustness and portability. For convenience, after the Pack-and-Go is exported, the *Maxwell Action* menu will revert to its previous setting. Note: Textures in external MXMs must be referenced correctly in the MXM or they will not be copied.

Quality/Performance

Time (min)

Specify the maximum time to process the rendering, in minutes. The quality of the rendering is determined by either the maximum render time parameter or the Sampling Level parameter— whichever is reached first will terminate the rendering (see below).

The more time reserved for a Maxwell render, the better the result will be (assuming that the full render time is used before the sampling level parameter is reached). However, the maximum render time parameter does not affect render quality directly, it only specifies the number of minutes the rendering will process before stopping. In other words, setting the maximum render time to 10 minutes and allowing the render to complete will yield the same result as setting the maximum render time to 100 minutes and stopping it after 10 minutes.

Sampling Level

Specify the target quality level for the render. Higher sampling level (SL) values will result in a more complete lighting solution and less noise in the rendered image.

The rendering will be stopped when either the sampling level is reached or the maximum render time is reached. Faster processors reach higher sampling values (i.e., a higher quality image) within a given amount of time than slower processors.

In Maxwell, the image is regularly updated during rendering. You can terminate a Maxwell render at any point in time, and save the resulting image at the time of render termination. For single image renders it is generally better to keep the sampling level limit high (the default of 25 works well); the render can always be stopped at any time if the result is satisfactory with a lower sampling level. Also, renderings can be resumed (processed further) later, by opening the MXI file in Maxwell and clicking on *Render*.

For animations, the sampling level is often set to a lower value and the maximum render time left high, so that a consistent sampling level is achieved for each frame.

CPU Threads

Specifies the number of threads that Maxwell Render is allowed to use. Normally this should be equal to the number of CPUs (Central Processing Units) available on the system. If this parameter is set to 0, Maxwell Render will use all available CPUs.

Lights

Multilight

[Off, Intensity, Color + Intensity]

Enables Maxwell's Multilight. Multilight is a unique and very useful feature that allows you to interactively adjust the intensity and/ or color of the emitters in the scene and to alter the ISO and shutter speed *during rendering or after the render has finished*. The adjustments may be keyframed and animated over

time, and a sequence of images can be saved. With Multilight, with just one rendering you can save different images of the same scene under different lighting conditions or make lighting animations.

Export Point and Cone lights

Enable to export Bonzai point and cone lights. If disabled, these light types will not be exported, regardless of the 'enable' setting on each individual light.

Geometry

Scene Scale

Specifies the scale of the scene, which affects the way the light travels in space. If this value is modified from the default (1), the render will become more or less dark, and the depth-of-field will be affected.

Allow Maxwell Studio to Export Geometry

This option allows the MXS file to be exported from Studio to other 3D formats later. If this option is disabled, the geometry from your Bonzai project is protected.

Textures

Disable Textures

Disables all textures in the rendering. This option is typically used to quickly check lighting and/or geometry. Disabling textures will dramatically speed up both the scene export process and the rendering itself.

Rendered Textures Resolution

During the export to the MXS process, Maxwell Render translates all the materials in the Bonzai project (that do not have a referenced MXM file) into Maxwell materials. Maxwell Render requires all textures to be based on image maps; therefore, procedural textures are converted into PNG files. This option specifies the resolution in pixels of the procedural textures rasterized to image maps. Using higher resolutions may result in better quality images, but will also require much more time to export from Bonzai, and more memory during rendering. To speed up the export process, use lower values, such as 512 x 512.

Globals

Dispersion

In this tab, the plugin provides controls to select if motion blur should be calculated for cameras and objects.

Displacement

In this tab, the plugin provides controls to select if motion blur should be calculated for cameras and objects.

Command Line

Specifies command options that affect the rendering process, including some lesser-used features not available through the graphical user interface of the plugin. For example, *low:p* launches the Maxwell Render process in low priority mode. Multiple commands may be entered on the same line. A full list of commands can be found in an appendix of the Maxwell Render manual.

Image

The options in this tab control the rendered image format, tone mapping, and the creation of optional render channels.

Scale

Scales pixel dimensions of output image by the factor shown here. Useful for creating quick draft renderings at lower resolutions.

Image Format

[PNG, Targa, JPEG, TIFF, JPEG2000, HDR, EXR, BMP] [8 BPC, 16 BPC, 32 BPC]

The image file format that the Maxwell render will be saved in. The image file format and bits-per-channel (BPC) are selected from the pull-down menus to the right. Not all BPC options are available to all image formats.

Color Space

Specifies the color space for the rendered image. Available color spaces include sRGB, Adobe RGB 1998, Apple RGB, NTSC, and many others. This parameter may be adjusted interactively in Maxwell while rendering.

Tonemapping

Burn

Parameter to control the highlights in a render. Lower burn values will decrease the intensity of the highlights to avoid “burned out” areas in the image. In most cases this parameter should be left at default. Lowering it too much may produce unnatural looking images. This parameter may be adjusted interactively in Maxwell while rendering.

Monitor Gamma


Maxwell Render internally uses a gamma of 2.2 to convert from spectral space to the RGB color space. This parameter is used to control the gamma conversion. Lower gamma values darken the image, while higher values lighten the image. Note that you can control this parameter interactively while rendering in Maxwell. This parameter may be adjusted interactively in Maxwell while rendering.

Channels

These options are used for advanced image compositing. Leaving all options off except for ‘Render’ will result in faster renderings. See the Maxwell Render manual section titled *Setting up the Render Output: Channels* for a full description of each channel.

Illumination and Caustics

These options are used to accelerate renderings when specific visual phenomena are not required for your image. These controls allow you to deactivate certain aspects of the rendering calculations, such as Indirect Light or Reflected Caustics. These options are also useful in cases where you want to see the effect of just the indirect light in the scene, and for compositing purposes.




Camera

Maxwell Render renders the active Bonzai view. To construct a Maxwell camera, the plugin obtains the eye point, center of interest, and focal length from the the Bonzai *View Parameters* (double-click on a view in the views palette). The resolution and pixel aspect ratio are obtained from the *Camera View* settings in View Parameters if these are in use; if not, the values specified in *Display > Image Options...* are used instead.

The Maxwell Camera Model

The Maxwell camera simulates the most important properties of a real-life physical camera, and as such requires several additional parameters not found in Bonzai. These are specified though the Camera Tab. The options here will apply to all views/ cameras in a scene. Maxwell Render options are stored on a per-scene basis, so if you need a different set of camera parameters, create a new Bonzai **Scene** in the *Scenes* palette.



Note: Maxwell currently only supports *3-Point Perspective* view types. Views similar to *2-Point Perspective* may be created using the plugin's *Shift Lens* feature. (Bonzai's *2-Point Perspective* does not model a shift lens-type camera, and so cannot be directly translated.)

Exposure

EV Lock

When enabled, the current exposure is maintained when adjusting the f-stop, shutter speed, or ISO. If the f-stop is adjusted, the shutter speed value will be adjusted to compensate, and vice versa. If the ISO is adjusted, the shutter speed will compensate.

f-Stop

Specifies the diameter of the lens opening, or *aperture*, as an f-Stop value. Clicking on the triangle to the right exposes a menu of traditional f-Stop values in third-stop increments. Arbitrary values can be typed into the text field.

f-Stop is a number representing the diameter of the aperture (d) in terms of the effective focal length (f) of the lens: $f\text{-Stop} = f/d$. For example, if a given lens has a Focal length of 30 and a lens Diameter of 60, then $f/d = 30/60 =$ an f-Stop of $f/0.5$. Using a smaller f-Stop value (bigger aperture) will allow more light to pass to the sensor, resulting in a 'brighter' exposure. Conversely, a higher f-Stop value (smaller aperture) will allow less light to pass and result in a 'darker' exposure.

The f-Stop system was conceived to establish a consistent exposure to light, regardless of the focal length of the lens being used. With this system, f/16 on a 1000mm lens will pass the same amount of light as f/16 on a 28mm lens.

Image exposure is determined by both shutter speed and f-Stop. (See *Shutter*, below.)

Aperture size also affects the *Depth of Field* (DOF) in your rendering. The smaller the f-Stop value (e.g., the bigger the aperture), the smaller the DOF, meaning that more of the image before and after the center of interest will be out of focus. See the Maxwell Render manual for an in-depth discussion of DOF.

- ✓ To experiment with the depth of field, produce any satisfactory exposure, then enable EV lock. Adjust the f-stop and make test renderings until you find a depth of field the suits your purposes.

Shutter

Specifies shutter speed, indicated as a fraction of a second. Clicking on the triangle to the right exposes a menu of traditional shutter speed values in third-stop increments. Arbitrary values can be typed into the text field. This parameter may be adjusted interactively in Maxwell while rendering.

The shutter speed determines how long the camera sensor will be exposed to light. For example, a shutter speed value of 1/60 will expose light to the camera sensor for 1/60th of a second.

As longer shutter speeds will expose a scene to the camera sensor for a greater period of time, moving objects may be blurred. If the camera itself is in motion, the entire image may be blurred. *Motion blur* may be controlled by varying the shutter speed. For instance, shutter speed of 1/1000th of a second will enable you to ‘freeze’ relatively fast motion, while the same motion shot at 1/8th of a second will probably result in significant motion blur. (If you follow a moving object with your camera and keep the shutter speed relatively low, the object you are following will remain sharp and the background will show motion blur.) Greater illumination will be required for a scene that is shot at a higher shutter speed, with daylight on a bright sunny day being ideal.

Image *exposure* is determined by the reciprocal relationship between the f-Stop value and shutter speed. A given exposure may be produced by any of many combinations of f-Stop and shutter speed. For example, 1/250 second at f/11, 1/500 second at f/8, and 1/1000 second at f/5.6 all provide equivalent exposures. However, there are compelling reasons for *prioritizing* either f-Stop or shutter speed (selecting a value for one and then adjusting the other parameter to get a satisfactory exposure). Prioritizing f-stop will allow you to achieve a specific DOF (i.e., ‘deep focus’ or ‘shallow focus,’ see *f-Stop*, above). On the other hand, prioritizing shutter speed allows you to finely control motion blur.

- ✓ Shutter speed may be interactively controlled in the Maxwell Render *Edit* pane. When a satisfactory exposure value has been found, copy the shutter speed value back to Bonzai.

Sensor

Sensitivity

Specifies the sensor’s sensitivity to light, as measured by the ISO arithmetic scale. Clicking on the triangle to the right exposes a menu of traditional ISO ‘speeds’ in third-stop increments. Arbitrary values can be typed into the text field. This parameter may be adjusted interactively in Maxwell while rendering.

The lower the ISO value, the less sensitive the sensor, requiring a more exposure to light (or stronger emitters) to achieve a satisfactory exposure. Conversely, higher ISO values require less exposure to light to achieve the same exposure.

In the real world, the sensor may be photographic film or a digital CCD; in Maxwell, the sensor is virtual. This means that, unlike in the real world, raising the Maxwell ISO will not add noise to the render.

Film Back

[Automatic, Manual]

[Automatic]: Selecting this option will cause the plugin to calculate the appropriate film back size to match Bonzai's focal length setting. Selecting this option will always result in a correct field of view match between the Bonzai viewport and the resulting Maxwell render.

Bonzai's focal length setting always assumes a 36mm wide film back, emulating the use of 35mm film in an SLR camera. The automatic option adjusts the film back height to match the aspect ratio of the pixel dimensions. For instance, a 500 x 1000 pixel image will be assigned a 36mm x 18mm film back, while a 1000 x 500 pixel image will result in a 36mm x 72mm film back.

[Manual]: Selecting this option allows for manual control over the size of the film back, in millimeters. The left parameter is the x (width) of the film, the right is the y (height).

Diaphragm

[Circular / Polygonal]

The diaphragm is the camera mechanism responsible for adjusting the size of the aperture. This option specifies whether the diaphragm is polygonal or circular. If set to polygonal, it will consist of a number of straight blades arranged in a circular pattern which are shifted to increase or decrease the aperture's diameter.

The diaphragm's geometry determines the shape of out of focus light in the rendering, a phenomenon known as the bokeh effect. The bokeh effect is most pronounced in images with a shallow Depth of Field, particularly around small highlights in out of focus areas, such as light distant sources or specular reflections.

Blades

Specifies the number of blades when a polygonal diaphragm is used. A diaphragm with six blades will produce typical hexagonal bokeh aberrations. A greater number of blades (or circular diaphragm type) will result in a more circular bokeh effect, but will require more render time.

Angle

Specifies the blade rotation angle in degrees. Rotating the angle of the blades will result in the polygonal bokeh shapes changing their general orientation.

Shift Lens

Specifies the shift of the film plane relative to the lens, as a signed percentage (-100% to 100%). The left parameter represents the x (horizontal) shift, the right the y (vertical) shift. Shift lens operates analogously rise, fall and shift with a view camera. Adjusting the y shift (rise) is useful in architectural rendering to eliminate converging parallels in tall buildings, approximating a two-point perspective.

Shift lens does not tilt or swing the film plane.

Simulens

The SimuLens system emulates a number of optical effects found in camera lenses.

Diffraction

Diffraction effects occur when light goes through small holes, causing interference patterns in the shape of the lens aperture. Light will always cause slight interference patterns because of the optical components used, causing the visual “artifact” known as glare.

This setting controls the intensity of the diffraction effect.

Frequency

Specifies the frequency of coloring in the diffraction effect. Higher values will make the patterns denser.

Aperture Map

The shape of the diaphragm will model the pattern of light that reaches the film. For example, a circular diaphragm will create circular patterns; a hexagonal diaphragm will create 6 light streaks. You can set the diaphragm shape using a black & white or color map called the aperture map. The map should be black, with white specifying the shape and size of the aperture.

Obstacle Map


Water drops, eyelashes or dirt on the camera lens will also cause diffraction effects. A black & white map called the obstacle map is needed. If you do not want to use an obstacle map, you can leave this path blank: you only need an aperture map for diffraction to work. However, if you do want to use an obstacle map, be aware that it is necessary to load an aperture map too. The map should be white, with black areas specifying dirt or scratches on the lens surface.

Note: The obstacle map and the aperture map must have the same resolution. Your render and the maps used do not always need to have the same resolution, but the more similar they are in resolution, the less diffraction distortion you will get.

Scattering

Scattering: Commonly known as bloom, scattering occurs when the light is scattered inside the lens before reaching the film.

Note: In almost all cases, you will NOT want to select the checkbox next to the three Simulens settings previously described. Doing so adds unnecessary processing time to each sampling level update, and increases RAM usage during rendering. Instead, wait until the render has reached an acceptable SL for viewing the Simulens effect, stop the render, apply a Simulens effect to give you an



idea of its influence, then disable Simulens again and resume the render. For adding Simulens effects to a range of MXI files after the render is completed, use File>MXI Batch Processing.

When you have determined appropriate *Diffraction*, *Frequency*, and *Scattering* values interactively in Maxwell, type those values back to this interface so you will not have to input them the next time.

Devignetting

Vignetting is an artifact that darkens an image around the edges, due to camera optics. Setting the devignetting parameter to 100% will eliminate the vignetting effect entirely; setting it to lower values will partially remove it.

In the real world, the more wide-angle the lens is (for example, a focal length of 24mm), the more pronounced the vignetting will be. As you raise the focal length of the camera, the vignetting effect will be less pronounced. A focal length of around 80mm or higher will have almost no vignetting, no matter the Devignetting settings used.

File

This tab specifies which files will be created upon initiating a Maxwell rendering, and where they will be stored.

Output File Paths

[Automatic, Manual, Image Only]

When a Maxwell rendering is made, the Bonzai project is translated into an MXS file. The resulting render may be stored as a standard bitmap image, as a high dynamic range Maxwell Image (MXI), or as both. There are three general ways to specify how and where these files will be saved, *Automatic, Manual, and Image Only*.

Output File Paths: *[Automatic]*

With Automatic filepaths, the plugin will automatically generate unique filenames and folders for your MXS, MXI, and Image files. using the automatic option ensures that you will never accidentally overwrite an important older file. Unique filenames, called the 'scene name stem', are generated as follows:

Bonzai project name + scene name + view name (or the text 'no view' if none is selected + a unique number to avoid naming collisions (incremented starting at 1).

The scene name stem is then appended with ".mxs", ".mxi", or the image file extension, as appropriate. If there are any illegal file characters in the project, scene, or view names, they will not be included in the filename. For 100% filename compatibility when exchanging files between platforms or remote servers, you have the option to automatically *replace* all blank spaces in the filename with either dashes or underscores. See *Render Options: Preferences* for details.

With Bonzai Project

When enabled, all automatically created folders and Maxwell output files will be created within the folder containing your Bonzai project.

Custom Location


When enabled, all automatically created folders and Maxwell output files will be created in the location specified in this field.



Select the custom output location.



Delete the custom path location.



MXI

When the *MXI* checkbox is enabled, an MXI will be saved. MXI is a high dynamic range format containing additional information such as Multilight settings. MXIs are unique in that their renderings can be stopped and resumed at any time, across multiple sessions. For details, see the Maxwell Render manual. If disabled, the *Image* checkbox must be enabled.

Image

When the *Image* checkbox is enabled, a bitmap image of the type and bit depth specified in *Image Output* (see *Render Options: Image*) will be saved. If disabled, the *MXI* checkbox must be enabled.

Folder per Bonzai Project

When enabled, a subfolder will be created for each Bonzai project, named as follows: Bonzai project name + “Maxwell”

Folder per Maxwell Scene

When enabled, a subfolder will be created with the scene name stem, minus the unique number at the end. If *Folder per Bonzai Project* is also checked, the Maxwell Scene folder will be created within that folder.

Create Dependencies Subfolder

When this option is selected, a folder for dependencies will be created inside the folder which receives the MXS. This can help to keep complex projects organized. (This option is not used with Pack-and-Go Scene, for maximum scene robustness and portability.)

Filename Construction

These checkboxes control how the automatic filename is composed. The timestamp option is recommended when doing network renderings; enabling this will avoid a situation where mxs files might otherwise be overwritten.

Output File Paths: [Manual]

The plugin will use the filenames and absolute filepaths you specify in the following fields for the MXS, MXI, and Image outputs.



Specify the name and location of the output path for a given field.



Delete the output path for a given field. If the MXI or Image filepaths are deleted, that file will not be saved. (At least one of the two must be specified or the plugin will report an error during the export process.)



To use the same output path and filename stem for all three fields, specify the MXS path first, then click on the copy icon. The image format is determined by the type specified in the *Image Format* pull-down menu (see *Render Options: Image*).

Create Dependencies Subfolder

When this option is selected, a folder for dependencies will be created inside the folder which receives the MXS. This can help to keep complex projects organized. (This option is not used with Pack-and-Go Scene, for maximum scene robustness and portability.)

Note that when the *Automatic* option is selected and a Maxwell Rendering is exported, the Manual filepaths specified here will be overwritten with the Automatic generated filepaths.

Output File Paths: [Image Only]

Often, you will not need the MXS or MXI files while working, and having them accumulate will only clutter your hard drive. With the *Image Only* option, the plugin saves the rendered image to the current project folder (or a custom folder) and avoids naming collisions automatically, so you'll never overwrite an important rendering.

Image Only keeps all the MXS files out of your way, storing them in a temporary, invisible folder which is deleted upon quitting Bonzai. MXI files are not saved.

The unique image filename is generated as follows:

Bonzai project name + scene name + view name (or the text 'no view' if none is selected + a unique number to avoid naming collisions (incremented starting at 1) + the selected image file extension

If there are any illegal file characters in the project, scene, or view names, they will not be included in the filename. For 100% filename compatibility when exchanging files between platforms or remote servers, you have the option to automatically replace all blank spaces in the filename with either dashes or underscores. See *Render Options: Preferences* for details.

With Bonzai Project

When enabled, the output image will be created within the folder containing your Bonzai project.

Custom Location

When enabled, the output image will be created in the location specified in this field.



Select the custom output location.



Delete the custom path location.

Prefs

This tab contains the plugin version and detailed compatibility information, as well as preferences.

Resources

Plugin Manual

Click to launch the plugin user manual.

Maxwell Manual

Click to launch the Maxwell user manual.

Generated Filenames

Convert Whitespace to

[spaces, underscores, dashes]

Controls how whitespace is treated in automatically generated filenames. For workflows that involve remote servers, you may wish to select 'underscores' or 'dashes,' for maximum filename compatibility.

Material Preview

Time (min)

The target time for the material preview, in minutes.

Sampling Level

The target Sampling Level for the material preview.


See the description of the *Time (min)* and *Sampling Level* parameters in the *Scene* tab for details about how these two parameters are related.

Use Fill Light

A 2' x 2' key light at camera left always illuminates the material preview object (sphere, cube, etc.). Enabling this checkbox adds a 2' x 2' fill light to the preview at camera right. Enabling the Fill light will result in a better material preview in most cases.

Use Kicker Light

Enabling this checkbox adds a 2' x 2' kicker light to the preview above and behind the material preview object. Enabling the Kicker light will provide a clear highlight along the top of the object, which is useful for certain shiny or metallic objects that otherwise may only reflect the empty (black) scene above.





"Ocean City Convention Center, Evening View," Craig Williams, Becker Morgan Group, Inc.

Lighting

The Maxwell for Bonzai plugin supports the export of the native *Point* and *Cone* light types. The plugin also adds several unique Maxwell light types: *Softbox*, *IES*, *Physical Sky*, *Sky Dome*, and *IBL*. All these light types may be created and edited through the Bonzai *Lights* palette and *Light Parameters* manager.

Point, *Cone*, *Softbox* and *IES* lights are emitter-based light sources, and are called Emitter Light Types in the following discussion. These types are intended for artificial lighting in interior lighting instruments and exterior night shots.

Physical Sky, *Sky Dome*, and *IBL* (Image Based Lighting) lights provide global environmental illumination throughout the scene, and are called Environment Light Types. These types are used for daytime exteriors and interiors with significant light penetration. *IBL* is also commonly used for photo-studio type interiors.

To create a new light, click on the 'plus' icon in the *Lights* palette. To change it to one of the Maxwell light types, double-click on the name of the light, then adjust the 'type' parameter in the resulting dialog. Click on the *Maxwell* item in the list on the right to edit the Maxwell-specific parameters of the light.

At least one light must be enabled before a rendering may be initiated.

Emitter Light Types

Point, *Cone*, *Softbox*, and *IES* light types create lamp geometry and MXM emitter materials behind the scenes when the Maxwell rendering is invoked. In the Lights palette, these types are indicated with pale yellow icons.


Parameters common to most of these types follow:

Intensity Tab Color

Selecting *RGB* will assign the color picker color to the emitter output. Alternately, select *Temperature* to specify the emitter output in degrees kelvin.

Intensity Tab Luminance

The luminance of the source can be specified via a number of industry-standard schemes, including by input power and efficacy, output lumens, lux, etc.



The intensity of light is delivered into the scene is affected by not only by the luminance, but also by the color and the emitter size (see *Parameters*, below). Check each of these parameters if you are getting unexpected results.

Shadows Tab

Maxwell emitters always cast shadows, so this option is removed when editing a Maxwell light type.

Parameters Tab Invisible Geometry

Enabling this option will cause the emitter geometry to be invisible to the camera in the Maxwell scene, though the emitter will still illuminate the objects around it.

Parameters Tab Quality

[1-Lowest - 5 Highest] Controls the number of faces (polygons) making up the emitter object. The default value (2) should work in almost all cases. Increasing this value may eliminate lighting artifacts, but will also increase render time.



Point and Cone Lights

The plugin can automatically translate Bonzai's *Point* and *Cone* light types into emitter-mapped geometries that Maxwell can use as light sources. In addition to the common parameters detailed in the previous section, *Point* and *Cone* lights have the following unique parameters:

Parameters Tab **Enabled**

If enabled, the light will be exported to the Maxwell scene; otherwise, it will only illuminate in Bonzai's 'Shaded' mode and not in the Maxwell rendering.

There is a global override for this setting which can be used to disable the export of all cone and point lights in the scene. See the lighting section in *Render Options: Scene*.

Parameters Tab **Diameter**

Sets the diameter of the emitter sphere (bulb). Geodesic spheres are used for an even of distribution and maximum efficiency.

SB

Softbox


The *Softbox* type is modeled on the photographic instrument of the same name, in which a bulb illuminates the subject through a rectangular diffusion screen, creating a localized, yet 'soft' light. The plugin equivalent is a rectangular plane which is mapped with an emitter material. The *Softbox* type is the fastest-rendering of the emitter type lights.

The Softbox will not only always point toward the center of interest, but will always remain level with the ground (XY) plane, regardless of the position of the origin or COI.

In addition to the common parameters detailed in the previous section, *Softbox* lights have the following unique parameter:

Parameters Tab **Width, Height**

The width and height of the softbox. The width is always level with the ground plane.




Softbox modeling space indicator shows actual size and direction

IES

IES

IES / EULUMDAT files specify the pattern of intensity and direction of emission from specific light fixtures. These files are available from manufacturers.

The base of the fixture, as defined by the IES / EULUMDAT file (e.g., the negative-Z axis), will always point toward the light's COI.



Relative intensity distribution pattern indicators for three IES files



By definition, it is not possible to change the intensity of an IES emitter, as this data is specified by the IES/EULUMDAT file. It is possible to change the color of the emitter, however.

Intensity Tab **IES**



Select the IES or LDT file.



Delete the path to the IES or LDT file.

A 2D representation of the distribution pattern is displayed below the filepath field.

Parameters Tab **Diameter**

Sets the diameter of the emitter sphere. The default size is recommended. Geodesic spheres are used for an even of distribution and maximum efficiency.

Parameters Tab **Spin**

This parameter controls the rotation of the fixture about the axis defined by the light origin and COI. The origin of rotation (0 degrees) always points 'down' to the ground plane (XY plane).

Parameters Tab **Length**

Controls the length of the IES distribution pattern indicator in the 3D modeling space.



"Ocean City Convention Center, Evening View," Craig Williams, Becker Morgan Group, Inc.

Environment Light Types

The Environment light types are dedicated to the accurate simulation of global and atmospheric light.

Multiple Physical Sky and Sky Dome lights may exist in a scene simultaneously, allowing for the setup of various shots at different times of day or under different atmospheric conditions. However, only one of these light types can be active ("shining") at a time.

Likewise, multiple IBL lights may exist at once, but only one may be active ("shining") at a time. If a Physical Sky light or Sky Dome is also active, the sky light will be used for any unused channels in the IBL. For example, if an IBL and a Physical Sky are both active, and the IBL uses only the background channel, the illumination, reflection, and refraction channels will be provided by the Physical Sky.

Physical Sky

Maxwell Render has a sophisticated atmosphere model that reproduces the skylight conditions at a given location locations at specific dates and times. The atmospheric parameters allow users to customize the appearance of the sky and the resulting light in the scene.

For a detailed discussion, see the Maxwell Render manual “Setting up environment lighting” chapter.

Intensity Tab Sun

Enables / disables direct sunlight. This parameter is linked to the lights ‘Shadows’ button in the Lights palette. If disabled, only ambient sky light will illuminate the scene.

Intensity Tab Power

Specifies the light output of the sun as a multiplier, where a value of 1 is equivalent to the the Earth’s sun. (i.e., A value of 2 would be twice that of the Earth’s sun, while a value of 0.5 would be half that of the Earth’s sun.)

Intensity Tab Temperature

Specifies the temperature of the sun’s spectral radiation, in degrees kelvin. The default value of 5777°K is the most common value measured outside the Earth’s atmosphere.

Intensity Tab Planet Reflectance

Specifies the percentage of light reflected from the planet surface back into the atmosphere. Changing this value will brighten / darken the overall sky and scene illumination with lower values giving a darker result. Common values are 26-32%.

Location Tab Sun Location

[Origin/COI, Altitude/Azimuth, Site/Time]



Specifies the scheme by which the sun will be located.

Sun Location: *[Origin/COI]*

The sun will be located according to the origin and COI parameters, and can be adjusted by moving the sun indicator in the 3D modeling space.

Sun Location: *[Altitude/Azimuth]*

The sun will be located by sun altitude, azimuth, and site rotation. Site rotation allows you to change the site north direction without rotating the model itself. In this mode, the Physical Sky will be automatically locked to avoid moving it within the modeling space.



Top: Sun Disabled indicator icon

Bottom: Sun Enabled indicator icon

Sun Location: *[Site/Time]*

The sun will be located by longitude, latitude, day, time, GMT offset, and site rotation. Site rotation allows you to change the site north direction without rotating the model itself. In this mode, the Physical Sky will be automatically locked to avoid moving it within the modeling space.

Parameters Tab *Ozone, Water, Turbidity Coefficient, Wavelength Exponent, Reflectance, Scattering Asymmetry*

These parameters affect the color distribution throughout the sky. For a detailed discussion, see the Maxwell Render manual “Setting up environment lighting” chapter.

Parameters Tab *Length*

Controls the length of the Physical Sky indicator in the 3D modeling space.



Sky Dome

Provides a uniform color or gradient dome to illuminate the scene. Sky Dome is appropriate for interiors with minimum exterior light penetration, and renders faster than Physical Sky.

Intensity Tab *Intensity*

Specifies the intensity of the Sky Dome in cd/m².

Intensity Tab *Zenith*

Click to specify the color at the zenith.

Intensity Tab *Horizon*

Click to specify the color at the horizon.

Intensity Tab *Midpoint*

The midpoint of the color gradient between the horizon (at 0°) and zenith (at 90°).

Intensity Tab *Sun, Temperature, Planet Reflectance*

These options function identically to those in Physical Sky (see previous section).

Location Tab *Sun Location*

[Origin/COI, Altitude/Azimuth, Site/Time]

These options function identically to those in Physical Sky (see previous section).

Parameters Tab *Length*

Controls the length of the Physical Sky indicator in the 3D modeling space.

IBL (Image Based Lighting)

Image Based Lighting allows you to light your scene by applying a high-dynamic range image (HDRI) to a virtual sphere that encompasses your scene. This is useful if you want your 3D model to appear as if it is actually in a real environment. The scene will be lit according to the properties of the HDRI and reflections from this environment will also show on your models. You can use an HDRI, MXI or EXR image for the IBL. These three image formats store high dynamic range data, providing accurate environment lighting. The images used for IBL should be in the Latitude/ Longitude format (the width should be twice the height). Images in “strokes” or “cross” formats will not work correctly.

There are four channels that may be mapped: *background*, *illumination*, *reflection*, and *refraction*. The same image can be mapped to all channels, or different images can be mapped to each channel.


It is not necessary to use all channels. If a channel is disabled, the active Sky Dome or Physical Sky will be used for that channel instead (or, if no sky is active, the channel will be unused).

Intensity Tab **Simple**

In simple mode, the same image is used for all four channels, and a single set of controls for rotation and scale affects all the channels equally. The channels can be enabled and disabled individually, however, and their relative intensities can be independently adjusted.


Intensity Tab **Detailed**

In detailed mode, each channel is completely independent from the others, and can be mapped with its own image, have unique rotation and scale parameters, etc.



 Select the HDRI, MXI or EXR file.

 Delete the path to the image file.

 View the image file.

Intensity Tab **Background**

When checked, the background channel will be enabled. This channel adds an IBL map that provides a background image for the scene. This channel does not provide any scene illumination or reflections.

Intensity Tab *Reflection*

The Reflection channel adds an IBL map for reflections on objects within the scene.

Intensity Tab *Refraction*

The Refraction channel adds an IBL map for refractions within objects in the scene.

Intensity Tab *Illumination*

The Illumination channel adds an IBL map for illumination.

Intensity Tab *Intensity*

Adjust the intensity of the map to increase or decrease its contribution to scene illumination, reflections, or refractions.

Intensity Tab *Rotation Azimuth, Rotation Altitude*

Rotates the spherical environment. (Degrees)

Intensity Tab *Scale Azimuth, Scale Altitude*

Scales the current map. (Multiplier)

Intensity Tab *Mapping*

[Spherical, Screen]

If spherical is selected, the background will be mapped to the entire spherical environment dome; if screen is selected, the image will be mapped to the width and height of the output image. This option is only available for the background channel in *Detailed* mode; in Simple mode, the background mapping will be spherical. The other three channels are mapped spherically in either mode.

Relative Efficiency of Light Types

In general, the Softbox type is the most efficient light type (it will clear noise in the image the fastest), followed by the *Point*, *IES*, and *Cone* types, in that order.

Sky Dome is faster than Physical Sky.

Lighting with Emitter-Mapped Objects

There are some cases, such as tube-shaped emitters, where the built-in light types may not be sufficient. In this case, model the emitter geometry in Bonzai, then apply an emitter material created in MXED to the object. See the chapter *Lighting With Emitters* in the Maxwell Render manual for more information about lighting in this manner.



“Restaurant,” Modeling and Rendering: Aaron Smithey Architectural Imaging

Materials

There are two approaches to working with Maxwell materials in Bonzai:

- *Translate Shaded*: Use Bonzai *Shaded* materials and let the plugin automatically translate them into Maxwell materials. This approach is very fast, and perfect for production projects where meeting a tight deadline is more important than perfectly accurate materials.
- *Referenced MXM*: Use Maxwell Materials (MXM files) directly. This approach allows you to leverage the full power and realism of Maxwell materials. Each Bonzai material can be set up to reference a unique MXM file.

Both approaches may be freely combined in a project. In a scene with many materials, it is usually easiest to let the plugin automatically translate most of the materials and use referenced MXMs only in cases where material accuracy is critical. All options are located in the *Maxwell* tab of *Material Parameters*.




Material Preview

To create a preview, select a sample object (6" sphere, 6" cylinder, 6" cube, or 6" plane), then click the green arrow button below the preview window. Because Maxwell previews can take some time, they are initiated 'on demand,' rather than updated continuously. A Maxwell render will be launched in the background, which will update the preview. The update process can be stopped at any time by clicking anywhere in the preview window, or by editing a control. (As of this writing, the render will continue in the background until complete, however.) The material preview target time, SL, and lighting can be adjusted in *Render Options: Prefs Tab*.

Using 'Translate Shaded'

Selecting this option will instruct the plugin to automatically translate the selected Shaded material into a Maxwell material. The resulting MXM will be embedded into the MXS scene file (i.e., it will not be saved separately) upon rendering.

To understand how the translation is performed, it is useful to first understand how Maxwell materials are defined. We recommend reading the chapter titled “Maxwell Materials” in the Maxwell Render manual before continuing with the section below.



If the Shaded material contains any embedded textures that do not have a valid reference on disk they will be automatically saved as PNG images. (This will be the case if the texture is a swatch generated by another renderer, or if an image file was been moved since it was first linked to the Bonzai material.)

Material Hint

By design, the Translate Shaded option is as reduced as possible; it hides all the complex details of MXM creation from the end user. It has been designed to provide good materials quickly and easily, to meet a demanding production schedule. Translate shaded offers a single control: *Material hint*, which controls how the Shaded material will be interpreted. In the images below, the Shaded render representation is on the left and the Maxwell translation on the right.

Material Hint Closest Match


The Closest Match material hint attempts to match the Shaded material as closely as possible, while still allowing enough flexibility to emulate a variety of materials. The description below provides a starting point for thinking about how to use Closest Match. Details have been omitted in the interest of clarity.

Closest Match creates a Maxwell material whose roughness is controlled by the Specular Roughness parameter. If Specular Roughness is set to 0, the material will be perfectly smooth, like a mirror. If set to 100, it will be perfectly rough, like a piece of uncoated paper.


Additionally, a clear gloss coat is applied over the base layer. The strength of this coating is controlled by the Specular Factor parameter. A value of 0 will result in no glossy reflection, while a value of 100 will result in a very glossy reflection.

To make a surface completely matte, set the Specular Factor to 0 (the Specular Roughness does not matter in this special case). This type of material (lambertian) renders very quickly.


If the Shaded material uses transparency, the material will become transparent as if it were made of a thin membrane, not a solid. (Specifically, Maxwell's transmittance parameter is not used, so materials will render quickly, but not refract light or generate caustics).




Hint: Closest Match
 Color: 197, 228, 254
 Ambient Factor: 100
 Diffuse Factor: 75
 Specular Factor: 0
 Specular Roughness: 0
 Specular Color: 255, 255, 255
 Transparency: 0
 Uses: paper, matte wall paint



Hint: Closest Match
 Color: 197, 228, 254
 Ambient Factor: 100
 Diffuse Factor: 75
 Specular Factor: 50
 Specular Roughness: 0
 Specular Color: 255, 255, 255
 Transparency: 0
 Uses: glazed tile, porcelain, lacquer, enamel paint



Hint: Closest Match
 Color: 197, 228, 254
 Ambient Factor: 100
 Diffuse Factor: 75
 Specular Factor: 50
 Specular Roughness: 25
 Specular Color: 255, 255, 255
 Transparency: 0
 Uses: powder-coat finishes, aluminized surfaces



Hint: Closest Match
 Color: 254, 69, 0
 Ambient Factor: 100
 Diffuse Factor: 75
 Specular Factor: 100
 Specular Roughness: 25
 Specular Color: 254, 147, 123
 Transparency: 0
 Uses: metallic paints


Closest Match Technical Summary: 2 layers, 1 BSDF per layer, ND 3.0 both BSDFS, Transmittance not mapped	
Shaded Parameter	MXM Mapping
Color	Base BSDF Reflectance 0° (attenuated); BSDF Reflectance 90° 255, 255, 255
Ambient Factor	Attenuates Color and Specular Color (not applied to bitmaps)
Diffuse Factor	Attenuates Color and Specular Color (not applied to bitmaps)
Specular Factor	Top Coat Layer Opacity/Mask (Layer is additive)
Specular Roughness	Top Coat Layer BSDF roughness
Specular Color	Top Coat Layer BSDF Reflectance 0° & Layer 1 BSDF Reflectance 90°
Transparency	Top Coat and Base Layer Opacity/Mask multiplier

Material Hint Architectural Glass - Normal, Architectural Glass - Clear


These material hints are used for fast-rendering architectural glass. In most cases, they will work well without adjustment. These materials will reflect, but not refract, light. This allows solid volumes to appear as if they were composed of a thin glass shell.

The color parameter controls the tint of the glass. The transparency parameter controls the layer weight.

The *Clear* variant applies an additional top coat to the glass which may be useful for some applications. Experiment with both types to see which works better for your application.



Hint: Hint: Architectural Glass, Normal
Color: 213, 243, 244
Ambient Factor: 100
Diffuse Factor: 75
Specular Factor: N/A
Specular Roughness: 0
Specular Color: N/A
Transparency: 80



Hint: Architectural Glass, Clear
Color: 230, 242, 241
Ambient Factor: 100
Diffuse Factor: 75
Specular Factor: N/A
Specular Roughness: 0
Specular Color: N/A
Transparency: 80


Architectural Glass, Normal Technical Summary: 1 layer, 1 BSDF, parameters in table below

Shaded Parameter	MXM Mapping
Color	Base BSDF Reflectance 0° (attenuated); Base BSDF Reflectance 90° (full color)
Ambient Factor	Attenuates Color (not applied to bitmaps)
Diffuse Factor	Attenuates Color (not applied to bitmaps)
Specular Factor	N/A
Specular Roughness	Base Layer BSDF roughness
Specular Color	N/A
Transparency	Top Coat and Base Layer Opacity/Mask multiplier


Material Hint Aluminum, Copper, Cobalt, Gold, Silver

The metals series creates efficient-rendering metals with minimal effort. The only parameters that need to be adjusted are the color and roughness.

For highly realistic metal materials, referenced MXM files with complex IOR files and bump or roughness maps are recommended.



Hint: Aluminum
Color: 195, 196, 197
Ambient Factor: 100
Diffuse Factor: 75
Specular Factor: N/A
Specular Roughness: 41
Specular Color: N/A
Transparency: 0



Hint: Gold
Color: 231, 136, 0
Ambient Factor: 100
Diffuse Factor: 75
Specular Factor: N/A
Specular Roughness: 0
Specular Color: N/A
Transparency: 0

Metals Technical Summary:

1 layer, 2 BSDFs weighted 60:40. ND, K, and Reflectance 90° set appropriately for each metal type


Shaded Parameter	MXM Mapping
Color	BSDF Reflectance 0°
Ambient Factor	Attenuates Color (not applied to bitmaps)
Diffuse Factor	Attenuates Color (not applied to bitmaps)
Specular Factor	N/A
Specular Roughness	BSDF 1 roughness; BSDF 2 attenuated (50%) roughness
Specular Color	N/A
Transparency	Layer Opacity/Mask multiplier

Material Hint **Water**


The water hint will work well without adjustment in most cases. Only the color and transparency parameters affect the material.

The color parameter controls the tint of the water. Note that the attenuation of light (transparency parameter) must be set to a relatively low value for the tint to be apparent.

The transparency parameter controls the attenuation of light through the water. At 1% transparency, half the light will be attenuated after 1 meter; at 100% half the light will be attenuated after 10 meters. If transparency is set to none (or 0) a default attenuation of 10 meters will be used.



Hint: Water
Color: 255, 255, 255
Ambient Factor: N/A
Diffuse Factor: N/A
Specular Factor: N/A
Specular Roughness: N/A
Specular Color: N/A
Transparency: 80



Hint: Water
Color: 140, 220, 224
Ambient Factor: N/A
Diffuse Factor: N/A
Specular Factor: N/A
Specular Roughness: N/A
Specular Color: N/A
Transparency: 10


Water Technical Summary:

1 layer, 1 BDSF. ND and K set appropriately for water; Reflectance 0° and Reflectance 90° set to 0,0,0; Roughness set to 0

Shaded Parameter	MXM Mapping
Color	BSDF Transmittance
Ambient Factor	N/A
Diffuse Factor	N/A
Specular Factor	N/A
Specular Roughness	N/A
Specular Color	N/A
Transparency	Attenuation, mapped 1m - 10m

Using 'Referenced MXM'

Each Bonzai material can be linked to an external Maxwell Material file (MXM) on disk. Maxwell will render using the referenced MXM instead of translating the Bonzai Shaded style.



Select the MXM file to reference.



Delete the path to the MXM file.



Copy the name of the MXM file to the Bonzai material name.



Edit the MXM in MXED, the Maxwell Material Editor application.

Use MXED preview

Enabling this option will use the preview embedded in the MXM by MXED, rather than the Bonzai sample scene.


Update 'Shaded' Renderer

Enabling this option will cause the MXM to be approximated in the OpenGL-based Shaded Full rendering representation. The system that translates the MXM into the very basic parameters available to the Shaded representation is sophisticated, but due to the nearly infinite ways that an MXM shader tree can be constructed, the result will occasionally be inaccurate and require adjustment.

Update 'Shaded' Renderer **Color Bitmap, #**

[None, Layer Opacity, BDSF Weight, Reflectance 0, Reflectance 90, Transmittance, Bump]

Often, it is desirable to see the MXM texture mapping on objects in the Bonzai space for purposes of scaling and alignment. Since bitmaps can be applied to almost any parameter in the MXM, the MaxwellZ plugin provides the ability to select the map(s) you wish to see Bonzai's OpenGL Shaded view, which supports two maps: one for color, and the other for transparency. If this parameter is set to *Reflectance 0*, for example, the texture map associated with that parameter (if one exists) will be used for the Shaded color texture map.



The number parameter indicates which map of a given type encountered will be used for the color texture. For example, if the Color Bitmap pulldown menu is set to *Reflectance 0*, and there are 3 BDSFs in the MXM, this number will indicate whether the first, second, or third *Reflectance 0* bitmap encountered will be used (counting from the top of the MXM tree downward).

If set to a high number which exceeds the number of maps for a given parameter (such as 100, the default), the last map encountered will be used. (In the *Reflectance 0* example above, if set to 100, it would use the third map.)

Update 'Shaded' Renderer *Transparency Bitmap*, #

[None, Layer Opacity, BDSF Weight, Reflectance 0, Reflectance 90, Transmittance, Bump]


These parameters work identically to the *Color Bitmap* and # above, but affect the Shaded representation's transparency channel, instead.

For most MXMs, the default settings for the 'Update Shaded' parameters will 'just work,' and will not need to be adjusted.

The Online MXM Gallery

In addition to making your own MXMs using MXED, you can take advantage to the large online library of materials hosted by Next Limit. Materials can be downloaded for free from:

<http://resources.maxwellrender.com/>




Maxwell Resources Site: <http://resources.maxwellrender.com/>

Tips for Materials and Texturing

Separate Maxwell materials may be applied to different faces of an object by assigning materials at face-level in the normal manner, with one exception: Maxwell Render requires that the emitters are applied to entire objects. An emitter material can not be applied at face level, otherwise the whole object will render black. This is not a limitation of the plugin, but the way the render engine works.

- Maxwell supports jpg, tga, bmp, tiff, and png image types for texture maps.
- Use file paths containing only letters, numbers, spaces, dashes, and underscores. Special characters (such as the bullet, •) will result in a 'file not found' error.
- To render materials with texture maps, objects using those materials must have texture coordinates applied. In Bonzai, the *Map Texture* tool is used for this. If the plugin detects objects without texture coordinates when creating the MXS, it will apply a set of default coordinates to those objects.
- To scale or rotate the texture on an object, use Bonzai's *Edit Textures* tool.
- If you have the Renderzone plugin installed, a bitmapped tile of each procedural texture is stored in memory for Bonzai's native Shaded Renderer to use. If the material is set to 'Translate Shaded', the plugin will save this swatch to disk when performing the Maxwell render. Texture mapping in the Maxwell rendered image will precisely match the OpenGL Shaded view.

"Robot Bob," Craig Williams,
Becker Morgan Group, Inc.





Organizing Dependency Filepaths


So that referenced MXMs work correctly, It is strongly recommend that Maxwell resources be organized and prepared in the following way:

- 1) Create a materials database *within your Documents folder*.
- 2) Put the MXM and all the bitmaps to which it refers in a subfolder with the same name as the MXM.
- 3) Double-click on the MXM file to load it into MXED.
- 4) Immediately choose 'Save' from the file menu, and close the MXM.

An example of correctly organized texture paths on the file system is shown at right.



 *Do not use intermediate folders to contain the bitmaps; they should reside in the same folder with the MXM.*

 *Do not put more than one MXM in a folder, unless it is absolutely necessary for both MXMs to depend on the same copies of each bitmap.*

Maintaining Dependency Filepaths

When transferring MXMs between workstations, or downloading MXMs from the Next Limit Materials Database, a problem may occur where MXMs cannot find referenced bitmap files. (As the MXMs still refer to the bitmaps located on the original author's computer.) When this happens, Maxwell will issue an error such as, "Bitmap example.tif not found."

The fix this problem:


- 1) Make sure you have followed step 2 in the section above, *Organizing Dependency Filepaths*.
- 2) Double-click on the MXM file to load it into MXED.
- 3) Immediately choose 'Save' from the file menu, and close the MXM.
- 4) Reference the MXM in a Bonzai material.

Maxwell Object Attributes

Apart from the main plugin (MaxwellZ), the installation package includes a second plugin called *Maxwell Attributes*. *Maxwell Attributes* allows the user to set several rendering parameters for each Bonzai object. These options are useful for post-process compositing with other images.

Editing an Object's Maxwell Attributes

To access the Maxwell attributes of a Bonzai object, select it with Bonzai's *Pick Tool*. Then, under the *Attributes* tab in the *Tool Options* Palette, select *Maxwell Attributes...* from the pulldown menu.



Currently, only one object may be edited at a time.

Hidden from camera

Enabling this option makes the object invisible to the camera, but still allows it to contribute to the lighting calculation (it will cast shadows, refract etc).

Hidden from Reflections / Refractions

When enabled, the object will not be reflected or refracted in other objects.

Hidden from Global Illumination

When enabled, the object will be visible, but it will not cast shadows or reflect light back onto other objects.

Exclude from Zclip planes

Normally, Maxwell follows Bonzai's clip hither and yon parameters, if they are enabled in *View Parameters*. When enabled, Maxwell the object will be excluded from clipping. Useful for technical illustrations and architectural renderings.



“Private Residence,” Modeling and Rendering: Aaron Smithey Architectural Imaging

Transferring Projects Between Workstations

Often it is necessary to share a Bonzai project with others in your office, or work on a project at both your office and home. Because Maxwell relies on dependencies (referenced files) that Bonzai proper is not aware of (and are therefore not copied using Bonzai’s ‘Save a Copy As...’ option), MaxwellZ has a special feature called *Pack-and-Go Project* which facilitates the transfer of all necessary files between workstations.

Using *Pack-and-Go Project*

1. Set your desired output folder using either Automatic or Manual filepath options. (The ‘Automatic’ is easiest to work with— and makes the most sense— when working on multiple workstations.)
2. In Maxwell Options/General, select ‘Pack-and-Go Project’ from the ‘Maxwell Action’ pulldown menu.
3. Select Display>Maxwell Render (or key shortcut equivalent).
4. All dependencies of the following types will be copied to the output folder: MXM, bitmap textures, and environment (HDRI) maps. (Note that MXS scenes and rendered procedural textures are not saved with Pack-and-Go Project, because these are not relevant when transferring a project to another workstation.)
5. After copying the the Bonzai project and dependencies to the second workstation
6. Open the Bonzai project. You will be asked to find the first missing MXM; after doing so, all remaining MXM paths will be automatically re-linked and updated. Note: you will still need to manually re-link each environment map your project references.

Importing Projects From FormZ 6

In Maxwell for Bonzai3d, a lot has changed from the 2.0.x plugin series, both for the end user and under the hood. formZ files imported into Bonzai will be updated to conform to the new system. Maxwell 2.5 plugin data cannot be read by the 2.0.x plugin.

Topic	Import Behavior	Things to Check and Adjust
Point and Cone lights	Point and Cone lights will be translated using the (greatly improved) new system.	<p>A default luminance value is applied, which may need adjustment</p> <p>Because the new translation of cone lights is much more accurate, inner and outer cone angles or the light's distance from the subject may require adjustment.</p>
Maxwell Render Options: Environment Tab	Depending on the old Environment settings, a Physical Sky, Sky Dome, or IBL light will be created. If the formZ 6 sun light was used to specify site and time, this data will be used to set the parameters of the Physical Sky or Sky Dome sun. The new environment lights will render identically to the 2.0.x system.	N/A
Surface Styles	Materials (formerly, 'Surface Styles') using referenced MXMs will render identically to the 2.0.x system. Auto-translated materials will offer richer results than the 2.0.x system (and will not match).	By default, the material hint is set to 'Closest Match.' The hint, and other 'Shaded' parameters may need to be adjusted for more realistic results.
Symbols	formZ's symbols are not imported into Bonzai3d (as of version 2.5).	N/A

Importing formZ 6 files containing Maxwell Data into Bonzai3d

Resources and Assistance

User Manual Access

This manual and the Maxwell Render Manual can be readily accessed for Bonzai via buttons located in the Maxwell Render Options 'Prefs' tab. Information on the plugin version may also be found there.

Software Updates

Maxwell Render and Bonzai Plugin Updates:

<https://portal.nextlimit.com/>

Training

Maxwell for Bonzai3d Video Tutorial Series by GetMethod:

<http://www.getmethod.com/blog/category/maxwell-render>

Introduction to Maxwell with Bonzai3d, an AutodeskSys webinar replay:

<http://www.youtube.com/watch?v=WzI6RSJLE5U>

Maxwell for formZ Video Tutorials by Intuition USA:

http://intuitionusa.com/maxwell_training.html

Forum Support

Maxwell for Bonzai forum hosted by AutoDesSys. Requires login to post, but not view. Not necessary to be a customer:

<http://www.formz.com/forum/discus41/messages/35953/35953.html>

Maxwell for Bonzai forum hosted by Next Limit. Requires login to view. Must be a Maxwell customer to post:

<http://www.maxwellrender.com/forum/viewforum.php?f=68>

Maxwell Materials

Next Limit Materials database:

http://resources.maxwellrender.com/visual_catalog.php?t=#page=1



"Art Gallery," Craig Williams, Becker Morgan Group, Inc.

Troubleshooting

Problem: Maxwell can't find the textures in my MXMs

Solution:

- Review the sections *Organizing Dependency Filepaths* and *Maintaining Dependency Filepaths* in this manual.

Problem: When Network Rendering, scenes are sometimes overwritten

Solution:

- Use *Automatic* filepaths, and enable the *Timestamp* option.

Problem: Maxwell rendering is too slow

Solutions:

- For test renders, use the 'Render Area Rectangle' to render a smaller section of the image, or set the *Scale* parameter in *Render Options/ Image* to a value less than 100%. Note that these two options may be combined.
- Disable Dispersion and/or Refractions.
- Disable any unnecessary Render Layers (In Render Options: Camera)
- Reduce the number of lights in the scene.
- Merge like emitters into a single object using the 'Join' tool (available in formZ only).
- Use simpler MXM materials. Lambertian (100% rough) materials will render very quickly; materials with complex IORs, translucency, and subsurface scattering take longer to clear noise.
- If you are only doing a lighting or geometry preview, check the 'Disable Textures' option (In Render Options: Export)

Problem: Export process is too slow

Solutions:

- Reduce the display resolution of smooth (ACIS) objects.

- Ghost any 'heavy' geometry which is not visible in the view.

Problem: Rendered scene is extremely dark (or black)

Solutions:

- Confirm that your camera exposure is correct.
- Maxwell's Emitters behave according to real-world parameters. Confirm that the Emitter power is sufficient. Don't forget efficacy for watt-based emitters.
- Confirm that your scene scale is realistic. 100W spread out over 100 sq. meters will result in a very dim scene.

Problem: Some MXM-referenced textures are not copied by Pack-and-Go

Bad texture filepaths within the MXM file often occur when you download an MXM from the internet, or and sometimes with MXMs found in the 'materials database' in the 'Maxwell 2' folder.

Solutions:

- Use the Fix Texture Paths function in the MXED and try the Pack-and-Go again.
- If this does not fix the problem, open the MXM and then immediately save it again.

Problem: Rendering exhibits triangulation artifacts

Maxwell Render works with triangulated, faceted objects only. When Bonzai's mathematically-defined ACIS (smooth) objects are encountered, the plugin will use the faceted representation of the ACIS object. This is the same representation that the Shaded render mode uses.

Solution:


- Adjust the Display Resolution *Facet Density* option. Increasing the facet density will usually resolve this issue, but will also result in longer export times. Use the minimum value that produces acceptable results, especially on complex objects.

Problem: Error 'There is no MAXWELL_ROOT environment variable on this machine'

Solution: This issue occurs on Windows systems only. If you encounter this error when attempting to load the plugin, it means that either:

- Maxwell Render is not installed on the machine. Download and install Maxwell Render to fix the problem.
- Maxwell Render is incorrectly installed on the machine. Uninstall/re-install Maxwell Render to fix the problem.

A System Environment Variable is a value that is available to every application on your computer. As such, the MAXWELL_ROOT variable points to Maxwell's home directory, and provides the ability for any application that wishes to locate



Maxwell to be able to do so. So, it is very important that it is correctly set when you install Maxwell. Usually this is no problem, but there are always cases where installation is not completely successful, and it is possible that you may need to manually create the variable. Note that you should proceed with caution when accessing Environment Variables. If you alter Environment Variables without having very specific reasons, you may encounter problems with the applications that rely on them.

Solution:

- To view your System's Environment Variables, go to: Start > right-click My Computer > Properties > Advanced > Environment variables. If Maxwell Render is installed correctly, there should be a MAXWELL_ROOT variable present, similar to the one shown. Note that the actual path may differ, depending on where Maxwell is installed on your machine.